CxAODFramework tutorial

<u>Daniel Büscher</u>, David Jamin for the Hbb group

Universität Freiburg

February 15, 2015

Outline

Outline

- Introduction to the framework
- ⇒ Session 1: setting up the code, run a test job
- Details on CxAODMaker
- ⇒ Session 2: adding a variable, read the output
- Details on CxAODReader
- ⇒ Session 3: adding histograms, making plots
- How to implement a new analysis
- ⇒ Session 4: adding packages and classes

Links and mailing list


- This tutorial builds up on the xAOD tutorial https://twiki.cern.ch/twiki/bin/view/AtlasComputing/SoftwareTutorialxAODAnalysisInROOT
- Framework TWiki https://twiki.cern.ch/twiki/bin/view/AtlasProtected/CxAODFramework
- https://twiki.cern.ch/twiki/bin/view/AtlasProtected/CxAODFramework
 Framework repository
 - https://svnweb.cern.ch/trac/atlasphys/browser/Physics/Higgs/HSG5/software/VHAnalysis/LHCRun2/CxAODFramework. The property of the property of
- HSG5 Framework mailing list: atlas-phys-higgs-hsg5Framework

Thanks Kristian for providing slides!

https://indico.cern.ch/event/373130/session/1/contribution/9/material/slides/0.pdf

Introduction to the framework


Run 2 workflow



Run 2 workflow

adapt the new analysis scheme given by the ASG

Run 2 workflow



Run 2 workflow

- adapt the new analysis scheme given by the ASG
- the CxAODFramework can process xAODs and DxAODs
- pruduce a small CxAOD ("C" for calibrated) or a Ntuple
- futher tools for reading the CxAOD, filling histograms and plotting are in place

Disclaimer

This framework is developed within the VHbb analysis group (HSG5). "Out of the box" compile/runtime configurations follow the VHbb analysis!

Usage

- For running the VHbb analysis, the code is simply checked out and run.
- For optimisation studies of the VHbb analysis, the code is checked out and modified.
 Optimisations are then merged into the repository.
- For other analysis, the code is checked out and used as the base for new derived analysis classes. More on this later...

Out of the box-contents

- The recommended calibrations are applied (CP tools).
- Overlap removal is performed (using official ASG tool).
- MET is rebuild.
- Object and event selections are applied.
- Systematic variations are run, i.e. the above steps are rerun for each variation.
- The output xAOD file contains the superset of objects among sys. variations, along with event level information.

Framework layout

Framework layout

- Based on RootCore (a C++ compilation framework which depends on ROOT).
- Uses EventLoop (EL) and SampleHandler.
- Currently there are 7 RootCore packages:

CxAODMaker	Main code for processing the input xAOD files, applying the calibration tools (CP tools), and writing the output CxAOD.
CxAODTools	Contains tools that are shared outside of the main CxAOD-Maker work-flow, such as object and event selection.
FrameworkExe	Contains the code for the executables for running CxAOD-Maker jobs, along with any associated configuration files.
FrameworkSub	Contains files relating to defining datasets and related information for tracking processing.
CxAODReader	Contains code to read CxAOD using the xAOD EDM (Event Data Model). Implements plotting style used in HSG5.
TupleMaker	Contains example code for producing a compact flat TTree based tuple that could be used for diagnostics or analysis.

TupleReader


read a compact flat TTree.

Contains the common TTree definition and example code to

Framework layout

Framework layout

- ullet Based on RootCore (a C++ compilation framework which depends on ROOT).
- Uses EventLoop (EL) and SampleHandler.
- Currently there are 7 RootCore packages:



CxAODMaker layout

EventInfoHandler

- Holds event level info, e.g. run/event number, GRL pass/fail, MC event weight, vertex info,...
- Visible to Particle Handlers

Note: Trigger info is still not accessible in current xAODs (JIRA)

Note: Each Handler retrieves/writes data from/to TEvent directly.

<Object>Handler

- <0bject> is: Electron, FatJet, Jet, Muon, Photon, Tau, TrackJet, TruthParticle.
- Applies calibrations (where appropriate) including sys. variations.
- Classifies particles and attaches corresponding flags to each particle for each sys. variation (HSG5 specific, e.g. 'isVHLooseElectron').

AnalysisBase

- · Controls the work flow.
- Defines the EL algorithm.
 - Contains the methods executed by EL, i.e. initialize(), execute()....
- Declares and executes all "handlers" and the "selector", i.e. these are plugged in to the EL work-flow through this class
- Has access to the TEvent, and pass it on to the Handlers

Note: "Object" is mostly for "physics object" or "particle"

METHandler

- Rebuilds the MET from calibrated objects, including sys. varations.
- Uses 'official' METRebuilder tool (which implements its own overlap removal.)

EventSelector

- Applies event level selection.
 Uses 'official' overlap removal
 tool for resolving conflicts for
 object appearing in multiple
 containers
- Apart from the overlap removal, the selection is HSG5 specific.

Calibration Tools

List of calibration tools in framework

Jets

- JetCalibrationTool
- JetCleaningTool
- JERTool
- JERSmearingTool
- BTaggingEfficiencyTool

Taus

- TauSmearingTool
- TauSelectionTool
- TauEfficiencyCorrectionsTool

Photons

- EgammaCalibrationAndSmearingTool
- AsgPhotonIsEMSelector

ASG analysis tools xAOD migration progress https://twiki.cern.ch/twiki/bin/viewauth/AtlasProtected/ASGUserAnalysisToolsxAODMigration

ASG analysis tools xAOD migration progress

Flectrons

- EgammaCalibrationAndSmearingTool
- AsgElectronLikelihoodTool
- AsgElectronIsEMSelector

Muons

- MuonCalibrationAndSmearingTool
- MuonSelectionTool
- MuonEfficiencyScaleFactors

Contents of the output CxAOD

The main guideline is to store as little as possible, which implies a trade-off

- The output file is (fairly) well organised, without too many variables creating confusion.
- Occasionally, this will also result in variables missing, and thus re-running of the code.

For particle-type objects


- The 4-vector is always stored.
- Other chosen quantities are explicitly added by hand (with 'decorators') and stored.
 (E.g. object scale factors, or flags for some selection criteria).
- The index of each particle in the input is also stored

Event information

- Run number, event number, NVtx3Trks, MCEventWeight,
- Eventually, also trigger information.


Systematic variations


- Stored with the original collection name plus the name of the variation after 3 "_".
 E.g "Muons__Nominal" and "Muons__someVariation".
- The uncalibrated collections are stored as well as "___Original"





Summary:

Shallow copies are made of the input (for nominal + systematic variations).










CxAODMaker configuration

CxAODMaker configuration

The configuration file is located here: FrameworkExe/data/CxAODMaker-job.cfg



TupleMaker

TupleMaker: produces flat ntuples

- int, float and arrays
- An EventLoop algorithm, like AnalysisBase in CxAODMaker.
- Configured independent of CxAODMaker: FrameworkExe/data/TupleMaker-job.cfg



Run with: hsg5frameworkTuple

- will run CxAODMaker followed by TupleMaker in one job
- the output collections from CxAODMaker are passed through TEvent to TupleMaker
- both, CxAOD and tuple, are written out

The systematic variations can be written out in 3 different ways


- "file": A separate file with one TTree for each variation
- "tree": One file with one TTree for each variation
- "block": One file with one tree, variables have the variation appended to their name

Note that some information might be lost from CxAOD to tuple

FrameworkExe

FrameworkExe

- Contains the files that defines the "main()" methods which are compiled into executables
 hsg5framework
 (runs CxAODMaker)
 hsg5frameworkTuple (runs CxAODMaker and TupleMaker in sequence)
 hsg5frameworkReader (runs CxAODMakerReader, which processes CxAODs)
- Configured in FrameworkExe/data/framework-run.cfg



Final note on runtime configuration

- The steering file is distributed to all the Handlers in CxAODMaker
- ⇒ modifying/adding configuration variables to a Handler is easy.

Session 1

- Check out and compile the code
- Run CxAODMaker and look at the output

Details on CxAODMaker

```
AnalysisBase : EL::Algorithm
histInitialize() 1/job
```

- AnalysisBase is an EventLoop algorithm
- ⇒ has pre-defined methods that are called in the job
- histInitialize() books 1 histogram: "MetaData_EventCount": holding event counts and sum of weights from the job and from DxAOD meta data
- no other histograms (and no cut-flow counter) currently

```
AnalysisBase : EL::Algorithm
histInitialize() 1/job
fileExecute() 1/file
```

- fileExecute() loads meta data from DxAOD and prints some basic info
- note that event loop seems to call the first fileExecute() before histInitialize()
- \Rightarrow we have a hack in place to ensure the desired order (histInitialize() first)

```
AnalysisBase : EL::Algorithm
histInitialize() 1/job
fileExecute() 1/file
initialize() 1/job
```

- initialize() is the main method for initializing the analysis
- it is split into several sub-methods to factorize the code (and easier derivation)...

```
AnalysisBase : EL::Algorithm
histInitialize() 1/jch
fileExecute() 1/fi
initialize() 1/jc
```

AnalysisBase

• initializeEvent() reads the configuration, prints sample info and books the output file

```
AnalysisBase : EL::Algorithm
histInitialize() 1/joh
fileExecute() 1/fi
initializeEvent()
initialize() 1/joh
initializeEvent()
```

- initializeEvent() reads the configuration, prints sample info and books the output file
- initializeVariations() reads the desired systematic variations from the config file

```
AnalysisBase : EL::Algorithm

histInitialize() 1/job

fileExecute() 1/fi

initializeVariations()

initializeHandlers()
```

- initializeEvent() reads the configuration, prints sample info and books the output file
- initializeVariations() reads the desired systematic variations from the config file
- initializeHandler() creates the object handlers: one for each collection of el, mu, jet...

- initializeEvent() reads the configuration, prints sample info and books the output file
- initializeVariations() reads the desired systematic variations from the config file
- initializeHandler() creates the object handlers: one for each collection of el, mu, jet...
- initializeSelector() books the "EventSelector", taking care of event selection and OR

- initializeEvent() reads the configuration, prints sample info and books the output file
- initializeVariations() reads the desired systematic variations from the config file
- initializeHandler() creates the object handlers: one for each collection of el, mu, jet...
- initializeSelector() books the "EventSelector", taking care of event selection and OR
- initializeTools() asks the object handlers to initialize their CP tools

- initializeEvent() reads the configuration, prints sample info and books the output file
- initializeVariations() reads the desired systematic variations from the config file
- initializeHandler() creates the object handlers: one for each collection of el, mu, jet...
- initializeSelector() books the "EventSelector", taking care of event selection and OR
- initializeTools() asks the object handlers to initialize their CP tools
- initializeSelection() determines which event selection should be run from the config file


```
AnalysisBase : EL::Algorithm
histInitialize() 1/job
fileExecute() 1/file
initialize() 1/job
execute() 1/event
```

- execute() is the main method that is called for each event
- in our design this method is quite compact
- ⇒ the heavy work is delegated to other classes...


```
AnalysisBase : EL::Algorithm
histInitialize() 1/job
fileExecute() 1/
initialize() 1/
execute() 1/
execute() 1/
setObjects()
```

- all calibration happens inside the object handlers, e.g. ElectronHandler
- the CP tools are created in initializeTools()
- setObjects() creates shallow copies of the input container
- one for each variation affecting this object type (only electron systematics for electrons)

- all calibration happens inside the object handlers, e.g. ElectronHandler
- the CP tools are created in initializeTools()
- setObjects() creates shallow copies of the input container
- one for each variation affecting this object type (only electron systematics for electrons)
- AnalysisBase::execute() loops over all object handlers and calls their setObjects()



- note that you won't find a setObjects() method in the ElectronHandler
- this method is the same for all object types, so it is defined in the ObjectHandler class
- ⇒ reduce duplication of code and avoid inconsistencies



- note that you won't find a setObjects() method in the ElectronHandler
- this method is the same for all object types, so it is defined in the ObjectHandler class
- reduce duplication of code and avoid inconsistencies
- ObjectHandler is a templated class: cannot be put into a vector (and is a bit hard to read)
- ⇒ there is another purely virtual ObjectHandlerBase, so we can fill a vector and do loops

- calibrate() calls the CP tools and applies the calibration to the shallow copies
- this is done for each object and systematic variation
- some information is decorated to the objects, e.g. a isVeryLooseLH flag for electrons

ObjectHandler

- select() calls a number of "pass" methods to select objects, e.g. passVHLooseElectron()
- properties of the objects are tested and the result is decorated, e.g. isVHLooseElectron
- special flag: passPreSel determines whether the object is used in the overlap removal

EventSelector

- the EventSelector is called after object selection (not to be confused with EventSelection)
- performSelection() implements a loop over all systematic variations:
- 1) the overlap removal is done for each variation
- 2) the event selection is called directly afterwards
- the event passes if at least one variation passes the selection
- the overlap removal writes a passORGlob to the objects:
 it is true if the object passed the OR in at least on variation

ObjectHandler

- fillOutputContainer() is called only if the event passes the selection
- the output containers are created and input objects are copied over:
- only objects that passed the selection, determined by a checkPassSel() method, are written
- the information that is written for each object is determined in setVariables()

```
AnalysisBase : EL::Algorithm
histInitialize() 1/job
fileExecute() 1/file
initialize() 1/job
execute() 1/event
```

AnalysisBase

- the METHandler and EventInfoHandler are not derived from ObjectHandler
- ⇒ their structure is a bit different, calls from execute() are separated
- if the event did not pass the selection wk()->skipEvent() is called
- ⇒ prevents that any other EL algorithm (i.e. the TupleMaker) is called after AnalysisBase for this event

```
AnalysisBase : EL::Algorithm
histInitialize() 1/job
fileExecute() 1/file
initialize() 1/job
execute() 1/event
postExecute() 1/sel.evt
```

AnalysisBase

• postExecute() is called only if the event has passed the selection, writes it to the output

```
AnalysisBase : EL::Algorithm
histInitialize() 1/job
fileExecute() 1/file
initialize() 1/job
execute() 1/event
postExecute() 1/sel.evt
finalize() 1/job
```

AnalysisBase

- $\bullet \ \ postExecute() \ is \ called \ only \ if \ the \ event \ has \ passed \ the \ selection, \ writes \ it \ to \ the \ output$
- finalize() closes the output file and prints some info

```
AnalysisBase : EL::Algorithm
histInitialize() 1/job
fileExecute() 1/file
initialize() 1/job
execute() 1/event
postExecute() 1/sel.evt
finalize() 1/job
histFinalize() 1/job
```

AnalysisBase

- postExecute() is called only if the event has passed the selection, writes it to the output
- finalize() closes the output file and prints some info
- histFinalize() writes the "MetaData_EventCount" histogram

Possibilities for object decoration

1) Directly via auxdata / auxdeco

- Very easy, it's a one-liner
- However, this is very slow (due to string hashing), wouldn't recommend to use it

```
electron->auxdata< float >("ptcone20") = 0.1; // for non-const objects
electron->auxdecor< float >("ptcone20") = 0.1; // for const objects
```

2) Using an Accessor or Decorator

- This is very fast (if the accessor/decorator is initialized only once)
- However, the declaration of the decorations can be distributed all over the code

```
static SG::AuxElement::Accessor< float > acce_ptcone20("ptcone20"); acce_ptcone20(*electron) = 0.1;
static SG::AuxElement::Decorator< float > deco_ptcone20("ptcone20"); deco_ptcone20(*electron) = 0.1;
```

3) Using a build in method of the object

- This should be fast (depends in the implementation)
- Not clear how it behaves for const / non-const objects

```
electron->setIsolationValue(0.1, xAOD::Iso::ptcone20);
```

4) Using our ObjectDecorator

- Uses Accessors / Decorators internally depending on const / non-const
- Is very fast and the definition of variables are gathered at one place

```
m_decorator.set(electron, ElecFloatProps::ptcone20, 0.1);
```

Would recommend to use method 3 if available and 4 otherwise!

Session 2

- Adding a new variable
- Grid running
- Run CxAODReader

Details on CxAODReader

CxAODReader layout

CxAODReader

- the main class is AnalysisReader, an EventLoop algorithm (similar to AnalysisBase in CxAODMaker)
- however, the structure is much simpler
- histInitialize() books the desired histograms
- initialize() sets the event selection, read sum of weights and cross sections
- execute() loops over all systematic variations and calls "fill" methods

Implication of shallow copies

- CxAODMaker stores an event / object if any variation passed
- ⇒ one has to re-run overlap removal, object and event selection in the reader

Updates in the trunk

- the CxAODReader has undergone some structural changes
- ObjectReader takes care of discovering and reading all variations for a given container
- HistNameSvc organizes histograms by name, e.g.
 SysMUONS_SCALE__1up/Zcc_pretag3jet_vpt0_pTB2_SysMUONS_SCALE__1up
- HistSvc makes booking and filling a histogram a one-liner:
 - m_histSvc -> BookFillHist("pTB2", 100, 0, 500, bdt_pTB2/1e3, m_weight);

Session 3

- Adding a new histogram
- Making plots

Implementing a new analysis

Strategy for new analyses

Strategy for new analyses

- The "base" code implements the VHbb analysis
- New functionality (e.g. a different object selection) is added by deriving new classes
- These classes can be put into new packages to separate the analysis

Example: modifying the muon selection

- Derive a new MuonHandler_Example from MuonHandler
- The new class inherits the functionality from the base class and can extend it, e.g. by a new "pass" method
- A new AnalysisBase_Example is needed to use the new handler
- Finally, a new executable is needed

Session 4

- Creating new packages
- Adding new classes
- Adding a new executable

Backup

Performance of CxAODMaker

Sample specifics

- HIGG2D4 DxAOD (2 lepton filter)
- 10000 ttbar events (2.3 Gb) (mc14.8TeV.117050.PowhegPythia_P2011C_ttbar.merge.DAOD_HIGG2D4.e1727_s1933_s1911_r5591_r5625_p1784)

Reading/writing

- ElectronCollection
- Muons
- AntiKt4LCTopoJets
- CamKt12LCTopoJets
- AntiKt4ZTrackJets
- MET_RefFinal

Configuration

- 10 systematic variations
- VHbb "2 lepton" event selection

Processing time (CPU time)

about 120 evt/sec

Disk space

• Output CxAOD file size 3.5 Mb (reduction factor: 650)